precisely

Release Notes

Version 8.2.12

This document describes the enhancements and modifications included in the latest release of Data360 DQ+, and highlights any changes that may affect your current implementation.

Contents:

New in 8.2.12	2
Fix pack installation - Enterprise only	
Contact us	3



New in 8.2.12

Note: This is an enterprise and single-tenant cloud release.

Corrected issues

Issue Summary	Issue Number
Fixed an issue where a case management search screen did not show a necessary horizontal scroll bar when the page was opened by following a hyperlink in an email about a specific case.	ISX-21583
Fixed a problem with AWS infrastructure creation via Terraform for RDS Aurora (Postgres Compatible) by using version 13.12.	ISX-21614

Fix pack installation - Enterprise only

Note: Fix packs are pushed to the cloud version of Data360 DQ+ automatically. The following steps only apply to the enterprise edition of the product.

To install this fix pack on the enterprise edition of Data360 DQ+:

- 1. Download the fix pack into the /tmp folder.
- 2. Give execute permission to the downloaded fix pack, for example: chmod 777 dqplus IS-8.2-202211230159-12-fixpack.sh
- 3. Extract the downloaded fix pack by running its name as a command, for example:

 $./{\tt dqplus_IS-8.2-202211230159-12-fixpack.sh}$

Extracting a fix pack for the first time will create a directory at:

/opt/infogix/dqplus-8.2/maintenance

4. Execute the ./apply-patch command from within /opt/infogix/dqplus-8.2/maintenance/dqplus_IS-8.2-202211230159-12-fixpack/bin.

8.2.12 Release Notes 2

To verify that the fix pack has been applied, navigate to the **Help** menu in the product and select **About**. The product's Updates information should be updated.

Reverting the fix pack

Execute the ./revert-patch command from within:
/opt/infogix/dqplus-8.2/maintenance/dqplus_IS-8.2-202211230159-12-fixpack

Contact us

If you encounter any technical issues, we recommend that you visit the support portal at support.precisely.com.

Community

Our product is constantly evolving and input from you is highly valued. If you have any suggestions, please contact the product team by submitting a feature request on the **Community**.

8.2.12 Release Notes 3



1700 District Ave Ste 300 Burlington, MA 01803-5231 USA

www.precisely.com

Copyright 2016, 2023 Precisely